


## Configure PerfectCue PC-Micro v 2.0



Connect a USB data cable to one of the “C” ports.


Launch the app.

Press Settings (⚙️), if requested. The Yellow LED blinks as the device exposes its memory to the computer and is recognized as a new, lettered drive – “PERFECTCUE”.



View the keystroke shortcuts associated with each transmitter button. These control presentations on connected computers.

Click a command. Enter a new keystroke such as [PG DN] or [SPACE], or a keystroke macro such as [Ctrl] [+]  
into the edit dialog. To disable a transmitter key such as the blank button, enter a null value.



**SAVE**

### Sound Cue (PortA)

Sounds are not available on this version of the PC-Micro.

### Light Cue Animation


Animations are not available on this version of the PC-Micro.

### Keystroke Delay

Slide changes can be delayed for up to 1 second after PC-Micro receives the wireless command. Why would you want this? See below\*\*.

**SAVE ALL SETTINGS**

If requested, eject the PerfectCue drive.



## Update the Firmware

### CHECK FOR UPDATE

Download and save a new version of the file "PerfectCue.zip" to your computer. It contains the firmware file "PerfectCue.bin" and a pdf file that explains new features or improvements.

Browse for the PerfectCue.bin file. Open. UPLOAD.

Unplug the USB cable(s). Reconnect. Test.

### Popular Shortcuts for Presentation Applications

Command	PowerPoint® (Windows)	Keynote® (MAC)	ProPresenter® (MAC)	
			Windows	MAC
Forward	RIGHT [▶]	DOWN [▼]	RIGHT [▶]	RIGHT [▶]
Back	LEFT [◀]	UP [⬆]	LEFT [◀]	LEFT [◀]
Screen Blank	[b]	[b]	F2	F2
Screen White	[w]	[w]		
Enlarge Image	[Ctrl] [+]	COMMAND [⌘] [≥]		
Start/Stop Video	[Alt] [P]	[SPACE]		

### \*\*Slide Change Delay

Have you ever been to an airport or a large train station? Important announcements are often preceded by a chime, a short musical motif, or a simple word like "Announcement!" These are designed to get travelers' attention before important information is delivered. Larger PerfectCue models have cue sounds that alert the audience. PC-Micro has no sounds. A delay can create a brief silence of the presenter's anticipation and helps cue viewers to a slide event.

